

## Termux control keys

```
Volume Up+E → Escape key
Volume Up+T → Tab key
Volume Up+1 → F1 (and Volume Up+2 → F2, etc)
Volume Up+0 → F10
Volume Up+B → Alt+B, back a word when using readline
Volume Up+F → Alt+F, forward a word when using readline
Volume Up+X → Alt+X
Volume Up+W → Up arrow key
Volume Up+A → Left arrow key
Volume Up+S → Down arrow key
Volume Up+D → Right arrow key
Volume Up+L → | (the pipe character)
Volume Up+U → _ (underscore)
Volume Up+P → Page Up
Volume Up+N → Page Down
Volume Up+. → Ctrl+\ (SIGQUIT)
Volume Up+V → Show the volume control
```

From:

<https://studie.famvisser.net/> - **Studie Pagina Chavoerah Maqor**

Permanent link:

[https://studie.famvisser.net/doku.php?id=s7\\_app\\_termux&rev=1468406582](https://studie.famvisser.net/doku.php?id=s7_app_termux&rev=1468406582)

Last update: **2022/05/06 21:58**

